

Workspace ONE UEM SCIM Adapter

Authors:

Matt Williams, VMware EUC Customer Success Architect

Joe Rainone, VMware EUC Consulting Architect

Latest Version: [1906.ga](#)

Validated through IdP's:

- Microsoft Azure Active Directory
- Okta (On Roadmap)


Latest news:

- Initial release now available for Azure AD provisioning

Overview

Workspace ONE UEM SCIM Adapter provides SCIM user/group management capabilities to Workspace ONE UEM. The middleware translates the System for Cross-Domain Identity Management, SCIM, to a CRUD REST framework that Workspace ONE UEM can interpret. This capability allows Workspace ONE UEM to synchronize cloud-based identity resources (users/groups/entitlements) without the need for an LDAP endpoint (service to service model). Examples include Azure AD,

Okta, and Sailpoint.



Prerequisites

Requirements

1. Node.js v7.6+ persistent runtime environment
2. Reverse proxy with SSL certificate (i.e. Apache, NGINX, HAproxy, etc)
 - The service does not accept SSL certificates and must be secured thru an SSL reverse proxy
 - Consider 60 minute timeouts depending on directory size
3. Connectivity from directory source (Okta, Azure AD, etc) to service over HTTPS 443
4. Workspace ONE UEM API information:

- Base API URL
 - Customer OG tenant code (REST API key)
5. Workspace ONE UEM 1810 or higher
 6. Resource object source anchors:
 - User -> ExternalId = ImmutableId (objectGUID or Ms-Ds-Consistency-Guid)
 - Group -> ExternalId = displayName
 7. Workspace ONE UEM Directory Services ->
 - 'Directory Type' must be set to 'None' at a minimum
 - 'Enable SAML Authentication For' set to 'Enrollment' at a minimum

Functions and Attributes

1. Not Enabled:
 - PATCH group modifications
 - Multi-group query pagination
 - Group membership query
 - Administrator account provisioning (On Roadmap)
 - Roles or Entitlements (On Roadmap)
 - Windows 10 Oobe Enrollment (On Roadmap)
2. Resource Attributes:

| Identity Provider | SCIM Adapter | Workspace ONE UEM |
|-------------------|--------------|-------------------|
| UserName | UserName | UserName |

| Source | Source | Source |
|--------------------------------------|------------|--------------|
| ExternalId = ImmutableId | ExternalId | ExternalId |
| Emails type eq "Work" | Emails | EmailAddress |
| | Emails | EmailUser |
| GivenName | GivenName | FirstName |
| FamilyName | FamilyName | LastName |
| Formatted = {GivenName + FamilyName} | Formatted | DisplayName |
| Active = IsSfotDeleted | Active | Status |

Installation

Install Node.js

Node.js is a prerequisite and must be installed on the server. Consider using a one-click container deployment, such as [Bitnami](#)

Linux: Either build from source or download from your distribution repo

Windows: [Download](#) the windows installer (.msi 64-bit) and install using default options.

Install Workspace ONE UEM SCIM Adapter

Create your own package directory e.g. /opt/ws1scim and copy the Adapter application within this `<package-root>`.

```
sudo mkdir /opt/wslscim
cd /opt/wslscim
sudo tar -zxvf <archivelocation>/wsl_uem_scim_adapter_1906
_beta.tar.gz -C /opt/wslscim/
```

Startup and verification

```
sudo node /opt/wslscim/index.js
```

Start a web browser or use an appropriate CLI client (note, IE does not support JSON content)

```
curl -vv http://localhost:9000/ping
=> Health check with a "hello" response
```

"Ctrl + c" to stop the Adapter

You can use the `/ping` URI as a health check endpoint for load balancers and reverse proxies.

Configuration

Edit the **plugin-airwatch.json** configuration file according to your needs.

Below shows an example of `/opt/wslscim/config/plugin-airwatch.json`

```
{
  "scimgateway": {
    "scimversion": "2.0",
    "loglevel": "debug",
    "localhostonly": false,
    "port": 9000,
    "auth": {
      "basic": {
        "username": null,
        "password": null
      },
      "bearer": {
        "token": null,
        "jwt": {
          "azure": {
            "tenantIdGUID": null
          },
          "standard": {
            "secret": null,
            "publicKey": null,
            "options": {
              "issuer": null
            }
          }
        }
      }
    }
  },
}
```

```
"certificate": {
  "key": null,
  "cert": null,
  "ca": null,
  "pfx": {
    "bundle": null,
    "password": null
  }
},
"emailOnError": {
  "smtp": {
    "enabled": false,
    "host": null,
    "port": 587,
    "proxy": null,
    "authenticate": true,
    "username": null,
    "password": null,
    "sendInterval": 15,
    "to": null,
    "cc": null
  }
},
"endpoint": {
  "entity": {
    "undefined": {
      "baseUrl": "https://your_api_server/api",
```

```
        "username": null,  
        "password": null,  
        "tenantCode": "your_aw-tentant-code"  
    }  
}  
}
```

You should only need to edit the following configuration items within the `plugin-airwatch.json` file:

- **port** - The Adapter will listen on this port number.
- **loglevel** - error, info or debug. Output to logfile
`/opt/ws1scim/logs/plugin-airwatch.log`
- **endpoint** - Contains endpoint specific configuration according to our **plugin code**. Place your Workspace ONE UEM API base URL i.e. `https://cn135.awmdm.com/api` and UEM API Tenant Code `Groups and Settings -> All Settings -> System -> Advanced -> API -> REST API -> API Key` into the corresponding fields

Manual startup

The Adapter can be started from a CLI running in administrative mode


```
sudo node /opt/ws1scim/index.js
```

<kbd>Ctrl</kbd>+<kbd>c</kbd> to stop

Automatic startup - Persistent

There are various flavors of Node.js persistent service tools. For example, you can start the Adapter persistently with `forever`:

```
cd /opt/ws1scim/  
sudo forever start ./index.js  
netstat -an | grep 9000
```

Other Installation Steps

Undocumented here; you will need to deploy a reverse proxy hosting SSL, and `ProxyPass` to `localhost:9000`. All connections from the source system will be on the public namespace, HTTPS.

Deployment examples:

- **Bitnami** - [Matt Williams](#)
- **Photon** - [Camille Debay](#)